

1. Launch the product via 1-click from AWS Marketplace. **Wait** until the instance status changes to 'Running' and passes all health checks. Then, connect to your instance using your Amazon private key and the 'ubuntu' user."

To update software, use: sudo apt update && sudo apt upgrade -y

When the instance boots, it automatically runs a first-boot wizard that configures Jitsi and starts the stack.

Choose one of two setup paths

#1: Use this if you don't have a domain ready yet.

- 1. In the EC2 Console, copy the instance's **Public IPv4 address**.
- Visit https://Your_Instance_Public_IP in your browser and accept the security warning (self-signed certificate).
- 3. Create a room name and share the link.

Note: Mobile apps and some clients may not trust self-signed certs. For the best experience, use a real domain (path B).

#2 (For domain + Let's Encrypt)

Use this for a trusted HTTPS certificate and best compatibility.

1. Create a DNS A record for your domain pointing to the instance's public IP

Example: meet.example.com \rightarrow 203.0.113.10

- 2. **SSH in** (from your terminal):
 - ssh ubuntu@<PUBLIC IP>
- 3. **Set your domain and email**, then re-run the wizard:

Edit the first-boot settings

sudo nano /etc/jitsi-firstboot.env

- # Set:
- # FQDN=meet.example.com
- # EMAIL=admin@example.com
- # (leave TZ=UTC or set your timezone; SELF_SIGNED=0)

Apply the changes (safe to run anytime) sudo systemctl stop jitsi-docker sudo /usr/local/sbin/jitsi-firstboot.sh --force sudo systemctl start jitsi-docker

Browse to https://meet.example.com.

Additional Info: Everyday commands

Restart Jitsi (safe) sudo systemctl restart jitsi-docker

Re-run the first-boot wizard after changing /etc/jitsi-firstboot.env sudo systemctl stop jitsi-docker sudo /usr/local/sbin/jitsi-firstboot.sh --force sudo systemctl start jitsi-docker

View container logs (pick one: web | prosody | jicofo | jvb)
sudo docker compose -f /opt/jitsi/docker-jitsi-meet/docker-compose.yml logs -f jvb

For extra Options:

Allocate Elastic IP

To ensure that your instance keeps its IP during restarts that might happen, configure an Elastic IP. From the EC2 console:

- 1. Select ELASTIC IPs.
- 2. Click on the ALLOCATE ELASTIC IP ADDRESS.
- 3. Select the default (Amazon pool of IPv4 addresses) and click on ALLOCATE.
- 4. From the ACTIONS pull down, select ASSOCIATE ELASTIC IP ADDRESS.
- 5. In the box that comes up, note down the Elastic IP Address, which will be needed when you configure your DNS.
- 6. In the search box under INSTANCE, click and find your INSTANCE ID and then click ASSOCIATE.

Your instance now has an elastic IP associated with it.